

# Configured Settings

## CCD Information

Customer Name: International Flavors & Fragrances Inc.  
CCD Name: International Flavors & Fragrances Inc.\_2070433  
Account Number: 2070433  
**Model/Solution: SP8400DN**  
CCD Type: Hardware  
CCD Number: 11525

## Manual Settings

| Full Path                                                                                                     | Value                                                                                                | Comments |
|---------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------|----------|
| Device Settings --> Email --> Email --> Administrator Email Address                                           | gps-device@iff.com                                                                                   |          |
| Manual Configuration --> General Configuration --> Dynamic settings --> Device Certificate                    | Validity Period 10 years Algorithm Signature Max key length supported by device (512/1024/2048/4096) |          |
| Manual Configuration --> General Configuration --> Dynamic settings --> SP Modes: Copy SP Modes               | SP 5-966-001 set to 1                                                                                |          |
| Network Settings --> Airprint --> AirPrint --> AirPrint                                                       | Inactive                                                                                             |          |
| Network Settings --> SNMPv3 --> Protocol --> SNMP                                                             | Active                                                                                               |          |
| Remote --> Remote Communications --> @Remote Registration --> Registration Options                            | DO NOT REGISTER: SNLX with @Remote Connector/ @Remote Connector NX                                   |          |
| Scanner --> Default Settings for Normal Screens (Classic) on Device --> Send File Type --> Send File Type     | Multi-page: PDF                                                                                      |          |
| Scanner --> Default Settings for Simplified Screens (Classic) on Device --> Send File Type --> Send File Type | Multi-page: PDF                                                                                      |          |
| Security --> Network --> SSDP --> IPV4                                                                        | Inactive                                                                                             |          |
| Security --> Network --> WSD (Device) --> IPV4                                                                | Active                                                                                               |          |
| SOP --> DEVICE --> Remote Panel Operation --> Remote Panel Operation - Manual                                 | Enabled                                                                                              |          |

SP Settings --> Copy SP Modes --> SP5 - 888  
--> 888 - Personal info protect 1: Protection for logs

SP Settings --> Copy SP Modes --> SP5 - 967  
- 001 --> 5-967-001 – Disable Document Server 1: OFF

SP Settings --> Printer SP Modes --> SP1-001  
--> 1001-006 bit 1 - Lock Sample print 1: ON

User Tools --> Administrator Tools -->  
General Settings --> Machine Data Encryption Settings/Encrypt Format All Data

User Tools --> File Transfer --> General  
Settings --> Administrators email address gps-device@iff.com

User Tools --> File Transfer --> SMTP -->  
SMTP Server Name smtp.global.iff.com

## Automatic Settings

| Full Path | Value | Comments |
|-----------|-------|----------|
|-----------|-------|----------|

|                                                                                                                                                  |    |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------|----|--|
| Device Settings --> Administrator<br>Authentication Management --> File<br>Administrator Authentication --> File<br>Administrator Authentication | On |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------|----|--|

|                                                                                                                                                                             |      |  |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|
| Device Settings --> Administrator<br>Authentication Management --> File<br>Administrator Authentication --> File<br>Administrator Authentication --> Administrator<br>Tools | true |  |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|

|                                                                                                                                                        |    |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------|----|--|
| Device Settings --> Administrator<br>Authentication Management --> Machine<br>Administrator Authentication --> Machine<br>Administrator Authentication | On |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------|----|--|

|                                                                                                                                                                                   |      |  |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|
| Device Settings --> Administrator<br>Authentication Management --> Machine<br>Administrator Authentication --> Machine<br>Administrator Authentication --> Administrator<br>Tools | true |  |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|

|                                                                                                                                                                          |      |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|
| Device Settings --> Administrator<br>Authentication Management --> Machine<br>Administrator Authentication --> Machine<br>Administrator Authentication --> File Transfer | true |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|

|                                                                                                                                                                                |      |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|
| Device Settings --> Administrator<br>Authentication Management --> Machine<br>Administrator Authentication --> Machine<br>Administrator Authentication --> General<br>Features | true |  |
|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------|--|

Device Settings --> Administrator  
Authentication Management --> Machine  
Administrator Authentication --> Machine  
Administrator Authentication --> Interface

true

Device Settings --> Administrator  
Authentication Management --> Machine  
Administrator Authentication --> Machine  
Administrator Authentication --> Maintenance

true

Device Settings --> Administrator  
Authentication Management --> Machine  
Administrator Authentication --> Machine  
Administrator Authentication --> Timer  
Settings

true

Device Settings --> Administrator  
Authentication Management --> Machine  
Administrator Authentication --> Machine  
Administrator Authentication --> Tray Paper  
Settings

true

Device Settings --> Administrator  
Authentication Management --> Network  
Administrator Authentication --> Network  
Administrator Authentication

On

Device Settings --> Administrator  
Authentication Management --> Network  
Administrator Authentication --> Network  
Administrator Authentication --> Administrator  
Tools

true

Device Settings --> Administrator  
Authentication Management --> Network  
Administrator Authentication --> Network  
Administrator Authentication --> File Transfer

true

Device Settings --> Administrator  
Authentication Management --> Network  
Administrator Authentication --> Network  
Administrator Authentication --> Interface

true

Device Settings --> Administrator  
Authentication Management --> User  
Administrator Authentication --> User  
Administrator Authentication

On

Device Settings --> Administrator  
Authentication Management --> User  
Administrator Authentication --> User  
Administrator Authentication --> Administrator  
Tools

true

Device Settings --> Email --> Email --> Auto  
Specify Sender Name

On

Device Settings --> Email --> Reception -->  
Max Reception Email Size

2

Device Settings --> Email --> SMTP --> SMTP  
Server Name smtp.global.iff.com

Device Settings --> Program/Change  
Administrator --> Administrator 1 --> Login  
User Name admin

Device Settings --> Program/Change  
Administrator --> Administrator 1 --> Login  
User Password 20r1c0h21

Device Settings --> Program/Change  
Administrator --> Administrator 2 --> Login  
User Name ricoh

Device Settings --> Program/Change  
Administrator --> Administrator 2 --> Login  
User Password 21!ffxx1

Device Settings --> Program/Change  
Administrator --> File Administrator -->  
Administrator 1 true

Device Settings --> Program/Change  
Administrator --> Machine Administrator -->  
Administrator 1 true

Device Settings --> Program/Change  
Administrator --> Network Administrator -->  
Administrator 1 true

Device Settings --> Program/Change  
Administrator --> User Administrator -->  
Administrator 1 true

Device Settings --> Program/Change  
Administrator --> User Administrator -->  
Administrator 2 true

Device Settings --> System --> General  
Settings --> Media Slot Use - Print from  
Memory Storage Device Prohibit

Device Settings --> System --> General  
Settings --> Media Slot Use - Store to Memory  
Device Prohibit

Network Settings --> Bonjour --> Bonjour -->  
IPV4 Inactive

Network Settings --> Community -->  
Community Name 1 --> Community name 20iFF%GpS21

Network Settings --> Community -->  
Community Name 1 --> IPV4 Active

Network Settings --> Community -->  
Community Name 2 --> Access Type read-write

Network Settings --> Community -->  
Community Name 2 --> Community name r1c0h#pCFS

Network Settings --> Community -->  
Community Name 2 --> IPv4 Active

Network Settings --> IPV4 --> Details -->  
DIPRINT Timeout Period 60

Network Settings --> IPV4 --> Details --> DNS  
Server Specify

Network Settings --> IPV4 --> Details --> DNS  
Server --> DNS Server 1 10.13.140.12

Network Settings --> IPV4 --> Details --> DNS  
Server --> DNS Server 2 10.13.140.10

Network Settings --> IPV4 --> Details --> DNS  
Server --> DNS Server 3 0.0.0.0

Network Settings --> IPV4 --> Details --> FTP Inactive

Network Settings --> IPV4 --> Details --> IPP Active

Network Settings --> IPV4 --> Details -->  
RHPP Active

Network Settings --> IPV4 --> Details -->  
RSH/RCP Active

Network Settings --> IPV4 --> Details -->  
SFTP Active

Network Settings --> IPV4 --> Details --> WSD  
(Device) Active

Network Settings --> IPV4 --> Details --> WSD  
(Printer) Active

Network Settings --> IPV4 --> Ethernet -->  
DHCP Inactive

Network Settings --> IPV4 --> Ethernet -->  
Domain Name Specify

Network Settings --> IPV4 --> Ethernet -->  
Domain Name --> Domain Name global.iff.com

Network Settings --> IPV4 --> Ethernet -->  
Primary WINS Server 000.000.000.000

Network Settings --> IPV4 --> Ethernet -->  
Secondary WINS Server 000.000.000.000

Network Settings --> IPV4 --> Ethernet -->  
WINS Deactive

Network Settings --> IPV6 --> IPV6 --> IPV6 Inactive

|                                                                                                            |                      |
|------------------------------------------------------------------------------------------------------------|----------------------|
| Network Settings --> SNMP --> Protocol --> IPv4                                                            | Active               |
| Network Settings --> SNMP --> SNMP --> SNMP                                                                | Active               |
| Network Settings --> SNMPv3 --> SNMP --> IPv4                                                              | Active               |
| Network Settings --> SNMPv3 --> SNMPv3 Setting --> Authentication Algorithm                                | MD5                  |
| Network Settings --> SNMPv3 --> SNMPv3 Setting --> Encryption Algorithm                                    | DES                  |
| Network Settings --> SNMPv3 --> SNMPv3 Setting --> Permit SNMPv3 Communication                             | Encryption/Cleartext |
| Network Settings --> SNMPv3 --> SNMPv3 Setting --> SNMPv3 Function                                         | Active               |
| Network Settings --> SNMPv3 --> SNMPv3 Setting --> SNMPv3 Trap Communication                               | Active               |
| Printer Settings --> Printer Basic Settings --> System --> Auto Continue                                   | On                   |
| Printer Settings --> Printer Basic Settings --> System --> Auto Continue --> Auto Continue Time            | 5                    |
| Printer Settings --> Printer Basic Settings --> System --> Auto Delete Store Print Jobs                    | On                   |
| Printer Settings --> Printer Basic Settings --> System --> Auto Delete Store Print Jobs --> Time(days)     | 1                    |
| Printer Settings --> Printer Basic Settings --> System --> Auto Delete Temporary Print Jobs                | On                   |
| Printer Settings --> Printer Basic Settings --> System --> Auto Delete Temporary Print Jobs --> Time(days) | 3                    |
| Scanner --> Send Settings --> Insert Additional Email Info --> Insert Additional Email Info                | On                   |
| Scanner --> Send Settings --> Insert Additional Email Info --> Insert Additional Email Info --> Language   | English              |
| Scanner --> Send Settings --> Max Email Size --> Set max email size                                        | On                   |
| Scanner --> Send Settings --> Max Email Size --> Set max email size --> Max email size                     | 35000                |

|                                                          |                |
|----------------------------------------------------------|----------------|
| Security --> IEEE 802.1X --> Domain Name --> Domain Name | global.iff.com |
|----------------------------------------------------------|----------------|

|                                           |          |
|-------------------------------------------|----------|
| Security --> Network --> Bonjour --> IPV4 | Inactive |
|-------------------------------------------|----------|

|                                           |        |
|-------------------------------------------|--------|
| Security --> Network --> DIPRINT --> IPV4 | Active |
|-------------------------------------------|--------|

|                                       |          |
|---------------------------------------|----------|
| Security --> Network --> FTP --> IPV6 | Inactive |
|---------------------------------------|----------|

|                                       |        |
|---------------------------------------|--------|
| Security --> Network --> LPR --> IPV4 | Active |
|---------------------------------------|--------|

|                                                         |          |
|---------------------------------------------------------|----------|
| Security --> Network --> NetBIOS over TCP/IPV4 --> IPV4 | Inactive |
|---------------------------------------------------------|----------|

|                                        |        |
|----------------------------------------|--------|
| Security --> Network --> RHPP --> IPV4 | Active |
|----------------------------------------|--------|

|                                           |        |
|-------------------------------------------|--------|
| Security --> Network --> RSH/RCP --> IPV4 | Active |
|-------------------------------------------|--------|

|                                        |          |
|----------------------------------------|----------|
| Security --> Network --> sftp --> IPV4 | Inactive |
|----------------------------------------|----------|

|                                                                        |    |
|------------------------------------------------------------------------|----|
| Security --> Network --> SNMP --> Permit Settings by SNMPv1 and SNMPv2 | On |
|------------------------------------------------------------------------|----|

|                                                       |        |
|-------------------------------------------------------|--------|
| Security --> Network --> SNMP --> SNMPv1, v2 Function | Active |
|-------------------------------------------------------|--------|

|                                          |        |
|------------------------------------------|--------|
| Security --> Network --> SNMP --> SNMPv3 | Active |
|------------------------------------------|--------|

|                                       |          |
|---------------------------------------|----------|
| Security --> Network --> ssh --> IPV4 | Inactive |
|---------------------------------------|----------|

|                                          |        |
|------------------------------------------|--------|
| Security --> Network --> TCP/IP --> IPV4 | Active |
|------------------------------------------|--------|

|                                          |        |
|------------------------------------------|--------|
| Security --> Network --> TELNET --> IPV4 | Active |
|------------------------------------------|--------|

|                                                                           |        |
|---------------------------------------------------------------------------|--------|
| Security --> Network --> WSD (Encrypted Communication of Device) --> IPV4 | Active |
|---------------------------------------------------------------------------|--------|

|                                                 |        |
|-------------------------------------------------|--------|
| Security --> Network --> WSD (Printer) --> IPV4 | Active |
|-------------------------------------------------|--------|

|                                                 |        |
|-------------------------------------------------|--------|
| Security --> Network --> WSD (Scanner) --> IPV4 | Active |
|-------------------------------------------------|--------|

|                                                                     |          |
|---------------------------------------------------------------------|----------|
| SOP --> PERSONAL --> Screen Device Settings --> Screen SD Card Slot | Inactive |
|---------------------------------------------------------------------|----------|

|                                                                        |          |
|------------------------------------------------------------------------|----------|
| SOP --> PERSONAL --> Screen Device Settings --> Screen USB Memory Slot | Inactive |
|------------------------------------------------------------------------|----------|

|                                                                                                                                    |    |
|------------------------------------------------------------------------------------------------------------------------------------|----|
| User Tools --> Administrator Authentication Management --> File Administrator Authentication --> File Administrator Authentication | On |
|------------------------------------------------------------------------------------------------------------------------------------|----|

|                                                                                                                                                            |      |
|------------------------------------------------------------------------------------------------------------------------------------------------------------|------|
| User Tools --> Administrator Authentication Management --> File Administrator Authentication --> File Administrator Authentication --> Administrator Tools | true |
|------------------------------------------------------------------------------------------------------------------------------------------------------------|------|

|                                                                                                                                                            |                 |
|------------------------------------------------------------------------------------------------------------------------------------------------------------|-----------------|
| User Tools --> Administrator Authentication Management --> User Administrator Authentication --> User Administrator Authentication                         | On              |
| User Tools --> Administrator Authentication Management --> User Administrator Authentication --> User Administrator Authentication --> Administrator Tools | true            |
| User Tools --> Administrator Tools --> General Settings --> Auto erase memory setting                                                                      | On              |
| User Tools --> Administrator Tools --> General Settings --> HDD Erase Method                                                                               | DoD (5220.22-M) |
| User Tools --> File Transfer --> General Settings --> Max reception email size                                                                             | 35              |